## Configuring Android OS Devices for Exchange 2010 IMAP

Updated 6/12/2013

NOTE: Not all Android devices, operating systems, and email applications are created equal. This document was configured using the Android OS 4.x. While configuration for other versions of Android should be similar, they may not follow this configuration documentation precisely.

- 1. If you are on-site and have WiFi enabled, make sure you have registered the device on the ANL WiFi network by opening your browser, browsing to any website, and filling out the web form that appears.
- 2. If you have a Zimbra mailbox already configured, it is recommended that you delete that account from your device before creating a new Exchange connection. This will prevent conflicts and duplicate messages.
- 3. Find the Settings icon on your device and click it. in the "Accounts" section, choose "Add Account"

	■ ₩ A I	(\$	1:06
Î۹Î	Settings		
0	Display		
	Storage		
î	Battery		
*	Apps		
2	Users		
PER	SONAL		
¢	Location access		
₽	Security		
A	Language & input		
Ð	Backup & reset		
ACC	OUNTS		
8	Corporate		
8	Google		
+	Add account		
SYS	ТЕМ		
0	Date & time		
*	Accessibility		
0	About tablet		
	Ĵ Î		

4. Choose "Email" as the account type

1		1:06
0		
	Add an account	
	Corporate	
	🤷 Email	
	8 Google	
*		

5. Enter your default ANL domain email address and password and click "Next". If you are unsure of you default email address, use <u>username@anl.gov</u>, where "username" is your ANL domain log in (i.e. the account you use to access the Inside Argonne web portal). Child domain addresses and accounts such as @aps.anl.gov, @mcs.anl.gov and @zimbra.anl.gov should not be used.

🖬 🖤 🛦 🖸 🛛 🤿 着 12:49
Account setup
Email account
You can set up email for most accounts in just a few steps.
Email address username@anl.gov
Password
Manual setup Next
qwertyuiop 🛚
asdfghjkl <sup>m</sup>
쇼 z x c v b n m , . 쇼
?123
$\sim$ $\Box$

6. Choose the account type "IMAP"

<ul> <li>Account setup</li> </ul>	<b>₹</b> ∎1:11
Account type	
What type of account is this?	
POP3	
IMAP	
Exchange	
Previous	
$\leftarrow$	

7. Configure the incoming server settings as shown in the screen shot below and click "Next".

Account setu	<b>() ()</b> () () () () () () () () () () () () ()				
Incoming server settings					
Username	migtest04@anl.gov				
Password					
IMAP server	mail.anl.gov				
Security type	SSL/TLS				
Port	993				
IMAP path prefix	Optional				
Previo	us Next				
q w e	rtyuiop 🕶				
a s d	fghjkl <sup>Done</sup>				
☆ z x	c v b n m , &				
?123 <b>•</b> /	com				

8. Configure the outgoing server settings as shown in the screen shot below and click "Next". Note the username does not include the @anl.gov suffix in this step.

Account s	<b>? ∎</b> 1:14			
Outgoir	ng server settings			
SMTP server	smtp.anl.gov			
Security type	STARTTLS			
Port	587			
🗹 Requ	🗹 Require sign-in.			
Username	migtest04			
Password				
Pre	vious Next			
q w e	rtyuiop 🕶			
a s	d f g h j k l Done			
仓 z x	c v b n m , . 企			
?123 🎐 🧔	com			

9. Configure additional account options and click "Next"



10. Enter your Display Name and click "Next" to finish the configuration